




# Crystal Application Tutorial: Initial calculations


## Load data




- Load the Crystal application (Click on the crystal application  on the top toolbar)
- Open the folder /RepTate/RepTate/data/Crystal/ and select the 3 files InitialTest\*\*\*.shearxs




- Drag and drop all files on to the Reptate window




- You should now see




## Run the model


- Load GO-polyStrand model (choose the model from the drop down list and then click the theory icon ). The calculation should take about 4 seconds.



- The default parameters are fine for this calculation so click compute



- You should see




- Set the both parameters  $G_C$  and  $N_0$   $1e-3$  to produce full agreement for  $N$  and  $\phi_x$ .

<input checked="" type="checkbox"/>	tau0	3.8e-10	inf
<input checked="" type="checkbox"/>	rhoK	2.7e+09	inf
<input checked="" type="checkbox"/>	G_C	0.001	inf
<input checked="" type="checkbox"/>	N_0	0.001	inf
<input type="checkbox"/>	beta	1	inf

### Things to try


- Change Gamma to adjust the sensitivity to shear
- Make *small* changes to epsilonB to adjust the quiescent barrier (equivalent to changing temperature)
- Adjust tau0 to scale all nucleation rates
- Adjust  $G_C$  to change the crystal growth rate

- Change the molecular weight distribution by clicking



and changing the relaxation times, number of modes, and concentrations (this needs to add up to 1).

- Double click on a data set and change the shear rate ( $\dot{\gamma}$ ) and shear end time ( $t_{stop}$ ) [T is temperature, which currently has no effect]



- Click the tabs on the left of the screen to make individual plots fill the window



- Use the 'View' menu towards the upper right corner to choose different views.

